



Master changed to Secondary – XP The Precinct Atlas

This procedure is intended to change a standalone master laptop to a secondary laptop.


On the computer you're converting, close Precinct Atlas and close all other open windows

Open the Control Panel






Click "Switch to Classic View" if you see this screen




Double-click "Network Connections"

For setups using **crossover cables** only:



Double-click "Local Area Connection"

For **wireless** setups only:




Double-click "Wireless Network Connection"



Scroll down and select "Internet Protocol (TCP/IP)"

Click Properties



Choose the 2nd bullet "Use the following IP address"

After IP address, enter 192.168.1.101

(If this will be the 3rd computer used in a precinct, use 192.168.1.102, etc. You'll also need to use a wireless access point (WAP) or a hub to connect 3 or more computers.)

After Subnet mask, enter 255.255.255.0


Click OK

Click OK


Close the window

Before continuing, pair your new secondary laptop with a master. Turn on the master laptop, and connect them (crossover cable or wireless).


Open the Control Panel




Double-click "Administrative Tools"




Double-click "Data Sources (ODBC)"



Click the "System DSN" tab



Click "Configure..."




After **Name** type “iavoter.sql”

After **Server** type “192.168.1.100\sqlexpress”

Click Next

(If a message box comes up asking you whether to overwrite, click “Yes”)




Choose the 2nd bullet “With SQL Server Authentication...”

After **Login ID** type “sa”

After **Password** type “sa”


Click Next



Check the box next to “Change the default database”


Select “iavoter” from the drop-down list

Click “Next”




Make sure that “Perform translation for character data” is checked

Click “Finish”



Click “Test Data Source...”



You should see a “successful” message like the one above. If you see a test failure, double check your settings (master and secondary) and retest.

Click “OK” after you have a successful test

Click “OK” to close both open windows

Close the Administrative Tools window